

valueType=	cmd=	option=	joints=	state=	stateText=	cond=	condValue=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description	Version
dbl.gps (lane needs Guidance Steering)		on								optional	optional	optional			VISIBILITY, EMITTER, ANIMATION, SLID	Active if GPS is turned on (Guidance Steering/GS or VCA)	2.0.0.0
		active								optional	optional	optional			VISIBILITY, EMITTER	Active if GPS is currently active (GS or VCA)	2.0.0.0
		lane+								optional	optional	optional			VISIBILITY, EMITTER	Active if current GPS-Lane is bigger than 0 (GS only)	2.0.0.0
		lane-								optional	optional	optional			VISIBILITY, EMITTER	Active if current GPS-Lane is smaller than 0 (GS only)	2.0.0.0
dbl.gpsLane (needs Guidance Steering)										optional	optional	optional			NUMBER, TEXT	Value of current GPS-Lane (GS only)	2.0.0.0
		delta								optional	optional	optional			ALL	Value of necessary course correction (-0.5..+0.5, GS only). Use factor for scaling.	2.0.0.0
		dir								optional	optional	optional			ANIMATION	Direction of course correction (-1: left, +1: right, GS only)	2.0.0.0
		dirLeft								optional	optional	optional			ALL	Active if direction of necessary course correction is left	2.0.0.0
		dirRight								optional	optional	optional			ALL	Active if direction of necessary course correction is right	2.0.0.0
dbl.gpsWidth		headingDelta								optional	optional	optional			ALL	Value of heading delta to gps course (GS or VCA)	2.0.0.0
										optional	optional	optional			NUMBER, TEXT	Value of currently set gps width	2.0.0.0
		mode								optional	optional	optional			TEXT	Value of ProSeed's mode in plain text	2.0.0.0
		mode		auto semi manual						optional	optional	optional			VISIBILITY, EMITTER	Active if proSeed's mode equals given state	2.0.0.0
dbl.proSeed (needs ProSeed)		distance								optional	optional	optional			NUMBER, TEXT	Value of tramLine distance	2.0.0.0
		laneDrive								optional	optional	optional			NUMBER, TEXT	Value of currently set lane	2.0.0.0
		laneFull								optional	optional	optional			NUMBER, TEXT	Number of lanes set	2.0.0.0
		tram								optional	optional	optional			VISIBILITY, EMITTER	Active if tramLines are created	2.0.0.0
		fert								optional	optional	optional			VISIBILITY, EMITTER	Active if fertilizer is enabled	2.0.0.0
		areaWork								optional	optional	optional			NUMBER, TEXT	Value of worked area	2.0.0.0
		areaField								optional	optional	optional			NUMBER, TEXT	Value of field size	2.0.0.0
		timeUse								optional	optional	optional			NUMBER, TEXT	Value of hectares per hour	2.0.0.0
		seedUse								optional	optional	optional			NUMBER, TEXT	Value of seed use	2.0.0.0
		segment		1 2 3 ...						optional	optional	optional			VISIBILITY, EMITTER	Active if segment choosen in state is enabled	2.0.0.0
		tramType								optional	optional	optional			VISIBILITY, EMITTER	Active if premarked tramlines are created	2.0.0.0
		audio								optional	optional	optional			VISIBILITY, EMITTER	Active if proSeed's audio signals are enabled	2.0.0.0
dbl.selection										optional	optional	optional	...-12 -10 1 2 ...		VISIBILITY, EMITTER	Active if currently selected vehicle/implement equals given selection	2.0.0.0
										optional	optional	optional		...-12 -10 1 2 ...	VISIBILITY, EMITTER	Active if currently selected group equals given selectionGroup	2.0.0.0
dbl.baler	isRoundBale	all any selected current	0 1 2 ... n S							optional	optional	optional			VISIBILITY, EMITTER	Active if bale is a round bale selected, baler setting, current: current bale	2.0.0.0
	baleSize	all any selected current	0 1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Value of current bale size selected: baler setting, current: current bale	2.0.0.0
	baleCountAnz	all any	0 1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Current value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)	2.0.0.0
	baleCountTotal	all any	0 1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Total value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)	2.0.0.0
	wrappedBaleCountAnz	all any	0 1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Current value of wrapped bales (requires Ifko's baleCounter Mod)	2.0.0.0
	wrappedBaleCountTotal	all any	0 1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Total value of wrapped bales (requires Ifko's baleCounter Mod)	2.0.0.0
dbl.lockSteeringAxe (needs lockSteeringAxe)	found		0 1 2 ... n S					1..n							VISIBILITY, EMITTER, ANIMATION, SLID	Active if steering axle lock is activated (requires Ifko's lockSteeringAxe mod)	2.0.0.0
	locked		0 1 2 ... n S					1..n							VISIBILITY, EMITTER, ANIMATION, SLID	Active if steering axle lock is activated (requires Ifko's lockSteeringAxe mod)	2.0.0.0
dbl.combineXP (needs CombineXP)	tonPerHour														NUMBER, TEXT	Value of currently processed tons per hour	2.0.0.0
	engineLoad														NUMBER, TEXT	Value of engine load	2.0.0.0
	yield														NUMBER, TEXT	Value of current yield	2.0.0.0
	highMoisture														VISIBILITY, EMITTER, ANIMATION, SLID	Active if high crop moisture is detected	2.0.0.0
dbl.frontloader	toolRotation	all any	1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Value of tool's rotation	2.0.0.0
	toolRotation	all any	1 2 ... n S		origin					optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized	2.0.0.0
	isToolRotation	all any	1 2 ... n S							optional	optional	optional			VISIBILITY, EMITTER, ANIMATION, SLID	Active if tool's rotation is between min and max	2.0.0.0
	isToolRotation	all any	1 2 ... n S							optional	optional	optional			VISIBILITY, EMITTER, ANIMATION, SLID	Active if tool's normalized rotation is between min and max	2.0.0.0
	toolTranslation	all any	1 2 ... n S							optional	optional	optional			NUMBER, TEXT	Value of tool's rotation	2.0.0.0
	toolTranslation	all any	1 2 ... n S		origin					optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized	2.0.0.0
	isToolTranslation	all any	1 2 ... n S							optional	optional	optional			VISIBILITY, EMITTER, ANIMATION, SLID	Active if tool's rotation is between min and max	2.0.0.0
	isToolTranslation	all any	1 2 ... n S		origin					optional	optional	optional			VISIBILITY, EMITTER, ANIMATION, SLID	Active if tool's normalized rotation is between min and max	2.0.0.0
dbl.print		<text>													TEXT	Prints value of <cmd>	2.0.0.0
dbl.miniMap	map														VISIBILITY	Displays miniMap on plane at node	2.0.0.0
	posMarker														VISIBILITY	Displays position marker on miniMap	2.0.0.0
dbl.cvt (needs VCTaddon)	drivingLevel			1 2 3 ...											ALL	CVT drive level	2.0.0.0
	accramp			1 2 3 ...											ALL	CVT acceleration ramp	2.0.0.0
	brakeramp			1 2 3 ...											ALL	CVT brake ramp	2.0.0.0
	trns pedal														ALL	CVT trns pedal activated	2.0.0.0
	pedalpercent			1 2 3 ...											ALL	CVT pedal percent	2.0.0.0
	digitalHandgasStep			1 2 3 ...											ALL	CVT handgas step	2.0.0.0
	autoDiffs														VISIBILITY, EMITTER		2.0.0.0
	preautoDiffs														VISIBILITY, EMITTER		2.0.0.0
	igmnactive														VISIBILITY, EMITTER		2.0.0.0
	motorColdLamp														VISIBILITY, EMITTER		2.0.0.0
	warmHeat														VISIBILITY, EMITTER		2.0.0.0
	warmDamage														VISIBILITY, EMITTER		2.0.0.0
	critHeat														VISIBILITY, EMITTER		2.0.0.0
	critDamage														VISIBILITY, EMITTER		2.0.0.0
	cvtWear														VISIBILITY, EMITTER		2.0.0.0
dbl.preFarming (needs PrecisionFarming)	rpmRange														ALL	CVT rpm range	2.0.0.0
	rpmDmin														ALL	CVT rpm min	2.0.0.0
	rpmDmax														ALL	CVT rpm max	2.0.0.0
	pHActual														NUMBER, TEXT	actual PH value	2.0.0.0
	pHTarget														NUMBER, TEXT	target PH value	2.0.0.0
	pHChanged														NUMBER, TEXT	PH value changed by	2.0.0.0
	nActual														NUMBER, TEXT	actual nitrogen level	2.0.0.0
	nTarget														NUMBER, TEXT	target nitrogen level	2.0.0.0
dbl.rda (needs tirepressure script)	nChanged														NUMBER, TEXT	nitrogen level changed by	2.0.0.0
	sprayAmountAutoMode														VISIBILITY, EMITTER, ANIMATION, SLID	spray amount automode	2.0.0.0
	applicationRate														NUMBER, TEXT	application rate	2.0.0.0
	soilType														NUMBER, TEXT	soil type	2.0.0.0
	cropSensor							optional							VISIBILITY, EMITTER	crop sensor active	2.0.0.0
	inflating														NUMBER, TEXT	Inflating / deflating is active	2.0.0.0
	pressure											optional			NUMBER, TEXT	actual pressure	2.0.0.0
	pressure	target										optional			NUMBER, TEXT	set pressure (target value)	2.0.0.0
	pressure	max										optional			NUMBER, TEXT	max pressure	2.0.0.0
	pressure	min										optional			NUMBER, TEXT	min pressure	2.0.0.0
	maxSpeed														NUMBER, TEXT	max speed allowed	2.0.0.0

valueType=	cmd=	option=	joints=	state=	stateText=	cond=	condValue=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description	Version
dbl.cc (needs extendedCruiseControl)	active			optional: 1 2 3											ALL	active if cruiseControl group is 1, 2 or 3 (state) or returns number	2.0.0.0
	speed			1 2 3											NUMBER, TEXT, ANIMATION, SLIDER		2.0.0.0
dbl.rds (needs realisticDamageSystem)	TotalNumberOfDamagesPlayerKnows														NUMBER, TEXT		2.0.0.0
	NextInspectionMonths														NUMBER, TEXT		2.0.0.0
	EngineLight														VISIBILITY, EMITTER		2.0.0.0